

HAPPY COTTON FREE PATTERN
VINTAGE VINYL



SIRDAR

WEST YORKSHIRE
EST. 1880

HAPPY


Cotton




**RETRO
AMIGURUMI
PROJECT**

HOW TO BASIC STITCHES

MAGIC RING



Make a loop with the yarn



Insert the crochet hook from the outside to the inside




Take the yarn with the crochet hook and pass it through the loop



Repeat the previous step to get two loops on the crochet hook. Take the yarn and pass it through both loops




Repeat until you have the number of stitches needed



Insert the crochet hook through the first stitch and make a slip stitch to close the ring


CHAIN STITCH

With the sliding knot on your crochet hook, cast on the yarn by passing it through the loop.




SLIP STITCH

Insert the crochet hook into the stitch, hook the yarn and take it through the two loops.




DOUBLE CROCHET

Insert the crochet hook through the stitch, hook the yarn and pull it through the loop; there will be 2 loops on the hook. Hook the yarn again and take it through both loops.



TREBLE CROCHET

Hook the yarn before inserting the crochet hook into the stitch and take it through the loop. Hook the yarn again and take it through the first two loops. Hook the yarn once more and pull it through the two remaining loops.




HALF TREBLE CROCHET

Hook the yarn before inserting the hook from front to back in the centre of the third chain. Hook the yarn and draw through 3 loops on hook. To repeat hook the yarn, insert hook in the centre of next chain, hook the yarn, draw yarn through stitch, hook the yarn draw yarn through 3 loops on hook.




TO INCREASE

Increasing is achieved by working two or more stitches in the pattern where there would normally be one stitch worked.



TO DECREASE

Insert the hook into the next stitch, wind the yarn round the hook and draw a loop through. Repeat this action into the following stitch (three loops now on the hook). Wind the yarn round the hook and draw it through all three loops.



VINTAGE VINYL SIZE



Width approximately 19cm, (7½in)
Depth approximately 12cm, (4¾in)
Height approximately 5cm, (2in)

MATERIALS

F234 Happy Cotton

● Colour A - 752	3 balls
● Colour B - 775	1 ball
● Colour C - 774	1 ball
● Colour D - 759	1 ball

- ✓ 3.00 Hook
- ✓ Stitch marker
- ✓ Tapestry needle
- Toy stuffing
- ✓ 1 pipe cleaner 18cm, (7in) in length
- ✓ Pins

TENSION

Exact tension not essential, keep stitches close together amigurumi style so no stuffing shows through gaps

ABBREVIATIONS

These instructions use UK crochet terms throughout - US terms are given in brackets below where applicable.

- ch - chain
- cm - centimetres
- dc - double crochet (US single crochet)
- in - inch(es)
- rnd(s) - round(s)
- ss - slip stitch
- st(s) - stitch(es)

VINYL RECORD

Using B make a magic ring.

1st Rnd. 6dc into magic ring.

2nd Rnd. Change to D, 2dc in each dc. 12dc.

3rd Rnd. (2dc in next dc, 1dc) 6 times. 18dc.

4th Rnd. Change to B, (2dc in next dc, 2dc) 6 times. 24dc.

5th Rnd. (2dc in next dc, 3dc) 6 times. 30dc.

6th Rnd. (2dc in next dc, 4dc) 6 times. 36dc.

7th Rnd. (2dc in next dc, 5dc) 6 times. 42dc.

8th Rnd. (2dc in next dc, 6dc) 6 times. 48dc.

9th Rnd. (2dc in next dc, 7dc) 6 times. 54dc.

10th Rnd. (2dc in next dc, 8dc) 6 times. 60dc.

Ss in next dc, fasten off and leave a tail for sewing.

TOP PART

Using D make 38ch.

1st Row. 1dc in 2nd ch from hook, 36dc, 1ch, turn. 37dc.

2nd to 25th Row. 37dc, 1ch, turn.
Fasten off and weave in end.

Using A work 1dc in each st around all 4 sides of the piece, working 3dc in every corner st.

Using colour A and back stitch, embroider a line all around the grey area of the top part (just between the grey and green colour).

Sew the vinyl record to the top part (referring to photograph and leaving 2 sts above, 2 sts below and 2 sts on the right side).

STONE ARM

Using D make 5ch, ss in 1st ch to make a ring.
1st Rnd. 1ch, 5dc into ring. 5dc.
2nd to 18th Rnd. 5dc.

Fold the pipe cleaner in half, insert it and cut the excess. Sew both ends so the pipe cleaner can't come out.

Sew the stone arm to the top part (refer to photograph) and bend the end around a little bit.

CONTROL PANEL

Using C, 11ch.
1st Row. 1dc in 2nd ch from hook, 9dc, 1ch, turn. 10dc.
2nd to 16th Row. 10dc, 1ch, turn.

Fasten off and weave in end.

Using C work 1dc in each st around all 4 sides of the piece, working 3dc in every corner st.

Sew the control panel to the top part (referring to photograph and leaving 2 rows above, 3 rows below and 1 st at the right).

Using B embroider 3 rows with chain stitch on the control panel as follows:-

1st row 4 rows up from bottom edge of control panel.

2nd row 4 rows up the 1st chain stitch row.

3rd row 4 rows up from the 2nd chain stitch row.

Leave 2 stitches at the right and 3 stitches at the left for every row.

Using D embroider 3 grey pitch controls with 3 straight stitches in the same place over the chain stitch rows.

Using A embroider 2 green buttons in the upper part of the control area with 3 straight stitches in the same place, 2 rows down from the top edge of the control panel.

BOTTOM PIECE

Using A make 38ch.
1st Row. 1dc in 2nd ch from hook, 36dc, 1ch, turn. 37dc.
2nd to 25th Row. 37dc, 1ch, turn.

Fasten off and weave in end.
With colour A work 1dc in each st around all 4 sides of the piece, working 3dc in every corner st.

FRONT AND BACK PIECES (Both alike)

Using A make 40ch.

1st Row. 1dc in 2nd ch from hook, 38dc, 1ch, turn. 39dc.

2nd to 7th Row. 39dc, 1ch, turn.

Fasten off and weave in ends.

SIDE PIECES (Both alike)

Using A make 27ch.

1st Row. 1dc in 2nd ch from hook, 25dc, 1ch, turn. 26dc.

2nd to 7th Row. 26dc, 1ch, turn. 26dc.

Fasten off and weave in ends.

TO COMPLETE

Join front piece and 1 side piece: place pins joining both pieces (wrong sides together) and with colour A work 7dc through two layers. The joining dc will show on the outside of the record player. Fasten off and weave in end.

Join the back part and the previous side part already joined: place pins joining both pieces (wrong sides together) and using A work 7dc through two layers. The joining dc will be on the outside of the record player. Fasten off and weave in end.

Join the remaining side part and the previous front and back pieces already joined: place pins joining both pieces (wrong sides together) and using A work 7dc through two layers. The joining dc will show on the outside of the record player. Fasten off and weave in end.

Join the bottom part to the previous parts already joined: place pins joining both pieces (wrong sides together) and using A work 1dc in each dc and 2dc in every stitch in the corner through two layers. The joining dc will show on the outside of the record player. Fasten off and weave in end.

Join the remaining top part in the same way you joined the bottom one and add stuffing as you go before you finish closing the part.

HAPPY COTTON BOOKS TO COLLECT

PLANES, TRAINS & AUTOMOBILES

HAPPY COTTON BOOK 14

Whatever your favourite mode of transport; luxury yacht, vintage steam train or (not very) jumbo jet, we think you'll wheel-y want to crochet them all.



CANDY SHOP

HAPPY COTTON BOOK 15

You'll be like a kid in a candy shop with these Happy sweets. From lollipops and liquorice to the poppiest popcorn, these amigurumi treats are too good to eat!



LOTS OF HAPPY COTTON PATTERN BOOKS TO COLLECT

HAPPY COTTON FREE PATTERN
VINTAGE VINYL
REF 2581



SIRDAR

WEST YORKSHIRE
Est. 1880

FOR MORE INSPIRATION

[f/knitsirdar](https://www.facebook.com/knitsirdar) [#SIRDARMAKES](https://www.instagram.com/SIRDARMAKES) [@knitsirdar](https://www.instagram.com/@knitsirdar) [p/knitsirdar](https://www.pinterest.com/knitsirdar)

www.sirdar.com



5 059474 125816 >